ABAP DUMP in /BNWVS/SAPLPARALLEL PROCESSING

If you receive the following ABAP dump

Category ABAP Programming Error

Runtime Errors UNCAUGHT_EXCEPTION

Except. /BNWVS/CX_GENERAL_ERROR

ABAP Program /BNWVS/SAPLPARALLEL_PROCESSING


```
Source Code Extract
 1 method CONSTRUCTOR.
   DATA: lt_config TYPE /bnwvs/cfg_c_tt.
    DATA: ls_grp_def TYPE /bnwvs/grp_def_c.
    ls_grp_def = /bnwvs/cl_config_provider=>load_grp_def( ac_group_def ).
    IF ls grp def IS INITIAL.
     RAISE EXCEPTION TYPE /bnwvs/cx_general_error
        EXPORTING
          textid = /bnwvs/cx_general_error=>noconfigfound.
10
    ENDIF.
11
   ii_wait_multiplier = 1.
12
13
   ic group def = ac group def.
14
15
   ii_wait_period = ls_grp_def-wait_period.
    ii_max_wait_period = ls_grp_def-max_last_period.
16
17
   ib_testonlyflag = ab_testmode.
18 endmethod.
```

Any error in class /bnwvs/cl_config_provider=>load_def is caused by the framework being unable to find configuration in the **Group Definition** area




This can be caused by the cached shared memory area not being up to date. To ensure it is perform the following steps:

1. Ensure all 3 PowerConnect jobs are stopped




2. Clear the shared memory component

Run tcode SHMM and ensure you invalidate the shared memory system wide for all /BNWVS/ memory segments



3. Ensure the BC SET is correctly activated with no errors



4. Restart the PowerConnect jobs



5. Ensure the shared memory component is reloaded

